




- To program the IMA codes of the injectors, select “4. Diagnostics tests”



- Select „6. Calibration Update“



- Select „2. IMA Code“



- The IMA Codes must be read directly from the injectors.

[4-6-2] - IMA codes Read - Write

<b>Cylinder 1</b> 8ZAB8IB	<b>Cylinder 2</b> 67ZV253
<b>Cylinder 3</b> 7GH61S4	<b>Cylinder 4</b> 8RA28AD

Write  Cancel

[hakoversuch] [ABC] E.C.U. initialization completed.

- Save the entry with the button "Write"

**Writing correctly done**

Exit 

- The programming of the IMA codes was successful as soon as the green window appears.
- Confirm with „Exit“.